

## MSIX App Attach

### On-ramp Guide





## What is MSIX App Attach?

MSIX app attach is a way to deliver MSIX applications to both physical and virtual machines. In simple words, it allows you to attach apps to the OS.

[Read more: What does MSIX App Attach do?](#)

## What is the MSIXMGR tool used for?

MSIXMGR takes an MSIX packaged application (.MSIX) and expands it into an MSIX image (VHD | VHDX | CimFS). That resulting MSIX image (.VHD(x) | CimFS) is what we upload to a storage account/file share in your AVD Deployment

## MSIX Image Creation with MSIXMGR Tool





## Prerequisites

### 1. A functioning Azure Virtual Desktop (AVD) deployment

[Azure Virtual Desktop MSIX app attach portal - Azure | Microsoft Learn](#)

### 2. A list of MSIX apps

if your apps are not in MSIX format:

- Refer to [the On-Ramp Guide on MSIX Packaging Tool](#) to convert apps to .msix




-

### 3. Download MSIXMGR Tool

You will need administrative permissions on the machine where you'll create the MSIX image



## Using MSIXMGR Tool

1. Post downloading, unzip the  msixmgr
2. Copy the location of the unzipped folder  C:\Users\username\Downloads\msixmgr\x64
3. Open a Command Prompt in elevated mode  Run as administrator
4. Navigate to the folder location copied in step 2.
5. Create a temp folder in C Drive. This is destination where the vhdx will be created.
6. Run the following command to unpack

```
msixmgr.exe -Unpack -packagePath <path to package> -destination <output folder> [-applyacls] [-create] [-vhdxSize <size in MB>] [-filetype <CIM | VHD | VHDX>] [-rootDirectory <rootDirectory>]
```

Example:

```
C:\Users\fizaazmi\Downloads\msixmgr\x64>msixmgr.exe -Unpack -packagePath "C:\Users\fizaazmi\Downloads\PBIDesktop_1.0.0.0_x64__8h66172c634n0.msix" -destination "c:\temp\PBIDemo.vhdx" -applyacls -create -vhdxSize 4500 -filetype "vhdx" -rootDirectory apps
Successfully created virtual disk
Stopping the Shell Hardware Detection service
Stopping dependent services if necessary.
Successfully initialized and partitioned the disk.
Formatting the disk.
Successfully formatted disk
Starting the Shell Hardware Detection service
Successfully started the Shell Hardware Detection Service
Finished unpacking packages to: c:\temp\PBIDemo.vhdx
```



## Using MSIXMGR Tool

Now that you've created the image, go to the destination folder and make sure you successfully created the MSIX image (.VHDX).


This PC > Local Disk (D:) > apps > PBIDesktop\_1.0.0.0\_x64\_8h66172c634n0 >


Search PBIDesktop\_1.0.0.0\_x64\_8h66172c634n0

<input type="checkbox"/> Name	Date modified	Type	Size
AppxMetadata	20-03-2023 03:20	File folder	
Assets	20-03-2023 03:20	File folder	
VFS	20-03-2023 03:21	File folder	
AppxBlockMap.xml	20-03-2023 03:20	XML File	4,071 KB
AppxManifest.xml	20-03-2023 03:20	XML File	26 KB
AppxSignature.p7x	20-03-2023 03:20	P7X File	2 KB
Registry.dat	20-03-2023 03:20	DAT File	1,976 KB
Resources.pri	20-03-2023 03:20	PRI File	6 KB
User.dat	20-03-2023 03:20	DAT File	52 KB
UserClasses.dat	20-03-2023 03:20	DAT File	232 KB




## Navigate to Azure Portal

1. Open portal.azure.com > Storage accounts > File shares > Select the fileshare >  Upload  
- Upload the MSIX Image created earlier.




2. Go to Properties and copy Share URL:





## Navigate to Azure Portal

1. Now go to Azure Virtual Desktop > Host pools> Select the Host Pool where you want to put the MSIX Apps
2. Under Manage section > MSIX packages >  Add
3. Paste the MSIX Image Path and select **Add** to interrogate the MSIX container to check if the path is valid
4. For Package applications, make sure the list contains all MSIX applications you want to be available to users in your MSIX package.
5. Optionally, enter a **Display name** if you want your package to have a more user-friendly in your user deployments.
6. Make sure the **Version** has the correct version number.
7. Select the **Registration type** you want to use depending on your needs:
  - **On-demand** registration postpones the full registration of the MSIX application until the user starts the application. This is the registration type we recommend you use.
  - **Log on blocking** only registers while the user is signing in. We don't recommend this type because it can lead to longer sign-in times for users.
8. . For **State**, select your preferred state.
  - The **Active** status lets users interact with the package.
  - The **Inactive** status causes Azure Virtual Desktop to ignore the package and not deliver it to users.


### Add MSIX package

Adding MSIX package notifies Azure Virtual Desktop that a new application has been made available for publishing and assigning.

MSIX image path *	<input type="text" value="\\advsharestorage.file.core.windows.net\msixfileshare..."/>
MSIX package *	<input type="text" value="Praat_1.0.0.0_x64_8h66172c634n0"/>
Package applications	PRAAT
Display name	<input type="text" value="PRAAT"/>
Version	1.0.0.0
Registration type	<input checked="" type="radio"/> On-demand <input type="radio"/> Log on blocking
State	<input type="radio"/> Inactive <input checked="" type="radio"/> Active



## Publish MSIX apps to an application group

1. Navigate to Azure Virtual Desktop > Application groups > Select application group you want to publish the app to
2. Under Manage, go to Applications > Add application  Add
3. Select Application source as MSIX package
4. For Application name, enter a descriptive name for the application
5. For Display name, enter a new name for the package that your users will see.
6. For Description, enter a short description of the app package.
7. If you're using a remote app group, you can also configure these options:
  1. Icon path
  2. Icon index
8. When you're done, select Save.
9. Assign users to the App group > Access Control (IAM) > Role assignments
10. Go to session hosts > Restart Virtual Machine

### Add application

Select an application from your start menu or add from a file path.

Application source \*

Start menu

Application \*

Start menu

Display name

File path

Description

MSIX package

Application path ⓘ

C:\Program Files\Microsoft Office\root\Office16\MSA... ✓

Icon path

C:\Program Files\Microsoft Office\Root\VFS\Windows... ✓

Icon index

0 ✓

Require command line

☒ No ☐ Yes

Save

Cancel





## Connect with us

1. [Join the MSIX Tech Community](#)

## Share your Feedback

1. [Submit Feedback on MSIXMGR Tool or App Attach](#)
2. [Submit Ideas and Feature Requests for MSIX App Attach](#)
3. [Start a discussion here](#)

## MSIX Packaging Tool

[On Ramp kit for MPT and PSF.docx](#)  
[\(sharepoint.com\)](#)

